

CelloSaaS – Evaluation Copy Activation User Guide



Table of Contents

1	REC	QUIREMENTS	.3
	.1	MINIMUM HARDWARE REQUIREMENTS	.3
CE	.2 LLOS	SOFTWARE REQUIREMENTS	.3 .4
CE	LLOS	AAS LICENSE DE-ACTIVATION1	0
UN	INST	ALL CELLOSAAS1	3
СС	NTAC	T INFORMATION1	4



1 Requirements

CelloSaaS is built using latest Microsoft technology stack and requires the pre-requisites to be installed on the user machine.

1.1 Minimum Hardware Requirements

Minimum 3 GHz processor.

Minimum 4 GB of RAM (Recommended 8 GB RAM).

1.2 Software Requirements

Developer Environment

- Windows Vista, Windows 7, Windows 8
- Microsoft .NET Framework 4.5
- ASP.NET MVC 4.0
- Microsoft Visual Studio 2012 Professional/ Premium / Ultimate /Express Editions
- Enterprise Library for .NET Framework 4.0
- Microsoft SQL Server 2008 and above

Deployment Environment

- Windows Server 2008 and above
- Microsoft .NET Framework 4.5
- ASP.NET MVC 4.0
- Enterprise Library for .NET Framework 4.0
- Microsoft SQL Server 2008 and above
- Windows AppFabric Distributed Caching Service [Optional]



CelloSaaS is yet to support Enterprise Library 5.0. Please do not install Enterprise Library 5.0 on your system for building or migrating applications using CelloSaaS.



CelloSaaS License Activation

Step1: Install all the necessary pre-requisite required to run CelloSaaS application.
Step2: Download the CelloSaaS Trial Package from our home page, <u>http://www.techcello.com</u>
Step3:

Organize 🔻 Burn New folder							
🔆 Favorites	Name	Date modified	Туре	Size			
🧮 Desktop	퉬 CelloSaaS Service Installers	9/26/2013 10:33 AM	File folder				
鷆 Downloads	퉬 CelloSaaS WCF Service	9/25/2013 2:04 PM	File folder				
🗐 Recent Places	CelloSaaSInstaller	9/26/2013 2:40 PM	Microsoft Visual Studio Extension	17,378 KB			
	DbScripts	9/26/2013 1:47 PM	Microsoft SQL Server Query File	2,071 KB			
🥽 Libraries	Release Notes	9/25/2013 5:26 PM	Text Document	4 KB			
Documents							
🌙 Music							
Pictures							
Culturation							

Step 4: Install the package by following the wizard



🔥 cellosaas







Step5: Open Visual Studio



Step 6: Create new Project





Step7: Select the CelloSaaS Web App template and name your project and click on OK.



Step8: The below screenshot shows a new project created using CelloSaaS Template.





Step9: Create a Database in the SQL Server

Step10: Run the DBScripts.sql present in the package to create the Cello Meta data store to

maintain the metadata information.

Step11: Get the **Connection String** and Update the same in the **sql.config** file in the "CelloSaaSConnectionString" Key.

For the purpose of evaluation:

You can paste the same connection string for all the other entries as well in case if you don't want to maintain a separate schema/db for each keys in the config file.





Step12: Compile and Run the application



Login Credentials

Company Code: company Username: admin@company.com Password: company#123

Trial License

This trial installation pack contains 15 days evaluation license. From the date on which you activate the Trial Product, Techcello grants You a limited, personal, non-exclusive, non-transferable revocable right to use the product to You to access Trial Product for evaluation purposes only. You shall not distribute any part of the product, whether in whole or in part. After the 15 days trial period, the evaluation product will automatically stop working. To know more about perpetual licenses and other offerings, please get in touch with the sales team at sales@techcello.com.



CelloSaaS License De-Activation

In case of migrating to a new server or de-activating an existing license, the following steps are to be followed.

Step1: Browse the application for example: http://provisioningapp.cello.com





Step2: Append the "/license/index" segment to the URL

← ⇒	×	D provisioningapp.cello.com/license/index	☆ =	≡
Apps	For qu	uick access, place your bookmarks here on the bookmarks bar. Import bookmarks now		

CelloSaaS

CelloSaaS License Information

License Details	icense Details		
License Type:	Production License		
Is Valid:	True		
Validity:	Infinite		
Operating System:	Windows Server 2008 R2		
System Info:	488E5F9176D210EC480e2FA9007ECDE29977E962AD95D46D4744041B5312A967F45DD148C494C7E656DD57EE3A3A57C3		
Activation Key:	1860BE92C6DB69E7A9F3AA894BDAA86F427B9AACD98A373FB45E1A330370C9CB773826FF05A4		
Company Name:	Techcello		
Customer Name:	CelloSaaS Team		
Customer Email:	cellosaas@techcello.com		
Phone Number:	(888) 706-1604		

De-Activate the product on this machine!

Copyright © 2012 by techcello.com, All Rights Reserved.

ing for provisioningapp



Step3: Click on the de-activate button and verify the "De-Activated Successfully" message in the page.

← → C [] provisioningapp.cello.com/License/Index?wa=Deactivate

CelloSaaS

CelloSaaS License Information

O De-Activated Successfully!			
License Details			
License Type:	Production License		
Is Valid:	True		
Validity:	Infinite		
Operating System:	Windows Server 2008 R2		
System Info:	488E5F9176D210EC480E2FA9007ECDE29977E962AD95D46D4744041B5312A967F45DD148C494C7E656DD57EE3A3A57C3		
Activation Key:			
Company Name:	Techcello		
Customer Name:	CelloSaaS Team		
Customer Email:	cellosaas@techcello.com		
Phone Number:	(888) 706-1604		

Go To Home De-Activate

☆ 🗉 🔳

Copyright © 2012 by techcello.com, All Rights Reserved.



Uninstall CelloSaaS

Uninstalling CelloSaaS is a three step process. They are

- 1. De-activate the license, Refer here
- 2. Uninstall the CelloSaaS Template from the Visual Studio Plugin Gallery
 - a. Open Visual Studio
 - b. Click on Tools Menu >> Click on Extensions & Updates (Refer the below screenshot)



- c. Click on uninstall against CelloSaaSInstaller
- d. Now the CelloSaaS template is successfully uninstalled from the machine.
- e. If you have created any CelloSaaS MetaData DB, kindly make sure you purge the MetaData DB.
- f. If you have created any CelloSaaS template based projects, kindly make sure you delete the project and related files entirely
- g. Uninstall the CelloSaaS Related Windows Services if you have installed any.



Contact Information

Any problem using this guide (or) using Cello Framework. Please feel free to contact us, we will be happy to assist you in getting started with CelloSaaS.

Email: <u>support@techcello.com</u> Phone: +1(609)503-7163 Skype: Techcello Support: support@techcello.com Timings: 9.00 AM – 5.00 PM IST [Monday- Friday]